
DRIVER INSTALLATION INSTRUCTIONS

APPLICABLE MODEL NUMBERS

- RZ09-03148

DRIVER NAME AND VERSION

Dolby Atmos APP Version 3.20402.409.0

INSTRUCTIONS

Note: This download is for the original driver that was installed on your Razer Laptop. Updates for this driver are available via standard Windows Updates. To ensure you have the latest driver installed on your Blade please make sure to apply all available updates from Windows.

Please follow the instructions below to download and install the original driver for your Blade. Following the installation, it is recommended to search for any available Windows Updates.

1. Ensure that your Blade is plugged into a wall outlet and not running on battery alone before proceeding.
2. Save any open documents on your computer and close all other programs before attempting this update.
3. Ensure that you have downloaded and installed the Dolby driver first before proceeding to the installation of the Dolby Atmos APP. You can download the driver and the app through the links below:


Dolby Driver: <http://rZR.to/9Tkqv>

Dolby Atmos App: <http://rZR.to/sIDOp>

4. Once you have extracted the file, proceed to the installation steps below.


INSTALLATION PROCESS

1. Right click on "DolbyPreload.bat" and select "Run as administrator"




| <input type="checkbox"/> | Name | Date modified | Type | Size |
|-------------------------------------|--|-------------------|--------------------|----------|
| <input type="checkbox"/> | 2a409f4c40c3462fa2e331a2852066d4.a... | 5/5/2019 11:47 PM | APPX File | 1,532 KB |
| <input type="checkbox"/> | 2a409f4c40c3462fa2e331a2852066d4_L... | 5/5/2019 11:47 PM | XML Document | 3 KB |
| <input type="checkbox"/> | AUMIDs.txt | 5/5/2019 11:48 PM | Text Document | 1 KB |
| <input checked="" type="checkbox"/> | DolbyPreload.bat | 9/7/2019 4:40 PM | Windows Batch File | 1 KB |
| <input type="checkbox"/> | Microsoft.NET.Native.Framework.2.0_... | 5/5/2019 11:48 PM | APPX File | 4,559 KB |
| <input type="checkbox"/> | Microsoft.NET.Native.Runtime.2.0_2.0.... | 5/5/2019 11:48 PM | APPX File | 220 KB |
| <input type="checkbox"/> | Microsoft.VCLibs.140.00_14.0.27323.0_... | 5/5/2019 11:48 PM | APPX File | 822 KB |
| <input type="checkbox"/> | MPAP_2a409f4c40c3462fa2e331a28520... | 5/5/2019 11:47 PM | PROVXML File | 2 KB |

2. Select "Run as Administrator" on the pop-up.



3. The User Account Control will appear on the screen. Select "Yes" to continue.



4. A command prompt will pop up on the screen. Wait for "Press any key to continue...", then press any key to complete the process.

